


IT-G400 Series

Android 6.0 Quick Start Guide

This document is a Development Guide Book for IT-G400 application developers.



No part of this document may be produced or transmitted in any form or by any means, electronic or mechanical, for any purpose, without the express written permission of CASIO Computer Co., Ltd. in Tokyo Japan. Information in this document is subject to change without advance notice.

CASIO Computer Co., Ltd. makes no representations or warranties with respect to the contents or use of this manual and specifically disclaims any express or implied warranties of merchantability or fitness for any particular purpose.

© 2017 CASIO Computer Co.,Ltd.

- The Bluetooth word mark and logos are registered trademarks owned by Bluetooth SIG, Inc. and any use of such
 marks by CASIO COMPUTER CO.,LTD. is under license. Other trademarks and trade names are those of their
 respective owners.
- Wi-Fi is a registered trademark of Wi-Fi Alliance.
- Android, Android Wear, Google, Google Play, Google Now and other marks are trademarks of Google Inc.
- Other company, product and service names used in this manual also may be trademarks or registered trademarks of others.

- Table of contents -

1. 0	lverview	_
1.1	Notes of this development kit	
1.2	Version of this development kit	3
1.3	Structure of the development kit	
1.4	About manuals	5
2. A	pplication development requirement······	6
2.1	Needed programing knowledges	6
2.2	Required hardware·····	
2.3	Required system·····	
2.4	Required softwares	8
3. In	stalling the development environment······	g
3.1	Installation steps of the development environment	g
3.2	Installing JDK	
3.3	Installing Android Studio	
3.4	Downloading Android SDK and USB driver	
3.5	Installing and Updating Device Library (AAR)	
3.5		17
3.5	5.2 Registering DeviceLibrary(AAR)	
3.5	5.3 Dependency check of DeviceLibrary (AAR)	20
3.5	5.4 Registering Help files (Javadoc)	
3.5	5.5 Updating of DeviceLibrary(AAR)	
3.6	How to use the DeviceLibrary (AAR)	27
4. A	pplication development and debug	
4.1	Enabling USB debugging	
4.2	Installing USB driver	29
4.3	Settings for ADB (Android Debug Bridge)	32

1. Overview

This document is a developement guide book writen for the IT-G400 application developers.

1.1 Notes of this development kit


Notes for using this development kit are as follows.

• There is a dependency between the version of Android Studio and the version of the DeviceLibrary. For details, refer to "2.4 Required softwares (p.8)" in the Quick Start Guide (this document).

Please contact your distributor to get the latest version of development Kit.

1.2 Version of this development kit

The version number of this development kit consists of a combination of major version and minor version, as shown below.



The major number represents the version of DeviceLibrary(i.e. DeviceLibrary.aarAAR).

So, when a newer version of development kit is released, if it includes newer version of DeviceLibrary, its major version number is increased, and the minor version is returned to zero.

If changes other than DeviceLibrary (i.e. manuals, tools, etc.) are included, its minor version number is increased.

1.3 Structure of the development kit

The following figure shows the structure of this kit.

QuickStartGuide.pdf	Read this document first.	
/MANUAL	/This folder contains manuals.	
QuickStartGuide.pdf	Quick start guide	
SoftwareManual.pdf	Software manual	
DeviceLibraryManual.pdf	Device library manual	
/SOFTWARE	/This folder contains softwares	
/BDK	/Basic development kit	
/CasioAndroidAddons	/Casio Addons for android	
/bin	/Program's folder	
CASIOAndroidAddons0100010005.apk	CasioAndroidAddons	
	(binary)	
/manual	/Manual's folder	
CasioAndroidAdons.pdf	Casio Android Addons	
	manual	
/DeviceLibrary	/Device Library's folder	
/javadoc	/javadoc's folder	
index.html	javadoc index file	
etc.	Other files.	
/bin	/Program's folder	
DeviceLibrary.aar	Device Library file	
	(binary)	
/samples	/Sample files's folder	
KeyLibrarySample.zip	KeyLibrary samples	
SymbolScan.zip	ScannerLibrary samples	
RangeScan.zip		
InverseScan.zip		
Centering Window Scan.zip		
TriggerScan.zip		
ImageCapture.zip		
/TOOLS	/Tools folder	
/KittingTool	/KittingTool folder	
/bin	/Program's folder	
KitSettings0100010008.apk	Backup/Restore settings	
KitDevice0100080008.apk	for Device setting	
KitApp0100010001.apk	for Application setting	
KitData.xls	Kitting scenario file	
/manual	/Manual's folder	
KittingToolManual.pdf	KittingTool manual	
/OSUpdateService	/OSUpdateService folder	
/bin	/Program's folder	
OSUpdateService0100000000.apk	OS Update Service	
/samples	/Sample files's folder	
OSUpdateSample.zip	OS Update Sample	

1.4 About manuals

The following is a list of manuals provided with this development kit.

Title	Contents	
Quick start guide	This document	
Software manual	Software specification of IT-G400	
DeviceLibrary manual	Describing the specifications of the device library	
CasioAndroidAddons manual	Describing the specifications of the	
	CasioAndroidAddons.	
KittingTool manual	Describing the specifications of the KittingTool.	

2. Application development requirement

2.1 Needed programing knowledges

IT-G400 application can be developped using the following language.

• Java

And, also the knowledge about the followings are needed.

- Android OS
- Android allication development
- Android Studio
- Networks, etc.

2.2 Required hardware

Product name	Remarks
IT-G400	

2.3 Required system

[Windows]

- Microsoft® Windows® 7/8/10 (32- or 64-bit)
- 3 GB RAM minimum, 8 GB RAM recommended; plus 1 GB for the Android Emulator
- 2 GB of available disk space minimum,
- 4 GB Recommended (500 MB for IDE + 1.5 GB for Android SDK and emulator system image)
- 1280 x 800 minimum screen resolution
- For accelerated emulator: Intel® processor with support for Intel® VT-x, Intel® EM64T (Intel® 64), and Execute Disable (XD) Bit functionality

[Mac]

- Mac® OS X® 10.10 (Yosemite) or higher, up to 10.12 (macOS Sierra)
- 3 GB RAM minimum, 8 GB RAM recommended; plus 1 GB for the Android Emulator
- 2 GB of available disk space minimum,
- 4 GB Recommended (500 MB for IDE + 1.5 GB for Android SDK and emulator system image)
- 1280 x 800 minimum screen resolution

[Linux]

- GNOME or KDE desktop
- Tested on Ubuntu® 14.04 LTS, Trusty Tahr (64-bit distribution capable of running 32-bit applications)
- 64-bit distribution capable of running 32-bit applications
- GNU C Library (glibc) 2.19 or later
- 3 GB RAM minimum, 8 GB RAM recommended; plus 1 GB for the Android Emulator
- 2 GB of available disk space minimum,
- 4 GB Recommended (500 MB for IDE + 1.5 GB for Android SDK and emulator system image)
- 1280 x 800 minimum screen resolution
- For accelerated emulator: Intel® processor with support for Intel® VT-x, Intel® EM64T (Intel® 64), and Execute Disable (XD) Bit functionality, or AMD processor with support for AMD VirtualizationTM (AMD-VTM)

Caution! The explanation after the next chapter is all for Windows. If you are using Mac or Linux as a development environment, you are responsible for building the environment at your own risk.

2.4 Required softwares

In order to develop IT-G400 application programs, it needs the development environment of Android.

Development platform (Recommended)

Development language	Development platform (Recommended)
Java	Android Studio 2.2 or above Android SDK (API level 17 - 23) Google USB driver JDK7 or above

Caution!

Using the old development kit with the new Android Studio may cause problems. Be sure to use the latest development kit when upgrading Android Studio version.

The combinations currently available are as shown in the table below.

Android Studio	2.2 or later		3.0 or later	
development kit	1.01 or later	1.02 or later	1.01	1.02 or later
OS	all version		←	

3. Installing the development environment

Due to version upgrade of Android SDK, environment may not be installed by the following procedure. In that case, please refer to the procedure described on Google's website etc. and build the environment.

3.1 Installation steps of the development environment

The followings are the basic steps to install the development environment.

(1) Installing JDK

Before installing Android Studio, JDK (Java Development Kit) has to be installed.

Regarding JDK, refere "2.4 Required softwares (p.8)".

Regarding JDK installation detail, refere "3.2Installing JDK (p.10)".

(2) Installing Android Studio

Install Android Studio to your PC.

Regarding the requirement of Android Studio, refere "2.4 Required softwares (p.8)".

Regarding Android Studio installation detail, refere "3.3 Installing Android Studio (p.13)".

(3) Downloading of Android SDK/USB driver

Download Android SDK and USB driver from Google via Android Studio.

Android SDK will be installed automatically after downloading.

Regarding USB driver installation detail, refere "4.2 Installing USB driver (p.29)".

Regarding the requirement of Android SDK, refere "2.4 Required softwares (p.8)".

(4) Setting of PATH

Add the path to Android SDK to "PATH" of the system environment variable.

For the setting method, refer to "4.3 Settings for ADB (Android Debug Bridge)(p.32)".

(4) Installing DeviceLibrary

Place the DeviceLibrary (AAR) to any where on your PC, and register it to the each of your projects via Android Studio.

Regarding DeviceLibrary installation, refere "3.5 Installing and Updating Device Library (p.17)".

(6) Application development and debug

Use the installed Android Studio and SDK to develop the application.

For details on how to use the device library, refer to "Device Library Manual".


To debug the application, connect the PC and the IT-G400 via the ADB (Android Debug Bridge) interface. For details, see "4 Application development and debug (p.28)".

3.2 Installing JDK

Java SE JDK can be downloaded from the Java site. Visit the site and download the Java SE JDK package corresponding to your Windows platform.


http://www.oracle.com/technetwork/java/javase/downloads/index.html

The URL and contents of the Java site may differ from the contents described in this document due to the update of the site. When downloading the JDK, please access the Java site via the search engine etc. and follow the description of the site.





In the following example, "jdk-8u121-windows-i586.exe" (64 bit) is downloaded. For the 32 bit Windows, 32 bit version of JDK must be needed.


* Because JDK is frequently updated, it's better to install the latest version at that time.



Execute the downloaded file with administrator privileges. Basically, it is not needed to change the value from default.









3.3 Installing Android Studio

Android Studio can be downloaded from Android site of Google.

http://developer.android.com/sdk/index.html




Agree to the "Terms of Conditions", then start downloading.



Once executing the downloaded file, follow the instructions to proceed the installation.

During installation, you will be prompted to specify the installation destination by the dialog below. The "Android SDK Installation Location" on the figure below is also necessary when installing the USB driver, it's better to take a note.




When the dialog shown below is displayed, installation of Android Studio is completed.




3.4 Downloading Android SDK and USB driver


Launch Android Studio, and chose "SDK Manager" from Configure tab.




Select "SDK Platform" tab, then check "Android 6.0 (API Level 23)".



Then, select "SDK Tools" tab and check "Google USB Driver".



Once agree to the "License Agreement", then press "OK" to start installation.



The downloaded files are stored under "Android SDK Installation Location" that you noted in "3.3 Installing Android Studio (p.13) ".

The USB driver is stored in "extras¥google¥usb driver" under "Android SDK Installation Location".

3.5 Installing and Updating Device Library (AAR)

This chapter explains how to register the device library and its help file to Android Studio project.


3.5.1 Preparations

Device Library (AAR) and its help files (Javadoc) are needed to be registered to the each project via Android Studio. Therefore, the method described here is necessary every time when creating new project that uses the device library.


The following chapter explains the procedure for registering the device library and its help files to the project. It is better to copy the DeviceLibrary and its help files from the IT-G400 Basic Development Kit to the local folder beforehand.

3.5.2 Registering DeviceLibrary (AAR)


Once open the project from the Android Studio, open the "New Module" dialog with [File] \rightarrow [New] \rightarrow New Module.




On the dialog shown below, select "Import .JAR/.AAR Package" and proceed with "Next".



Press the of "File name" and select the DeviceLibrary (AAR) you copied beforehand.



By the above, the registration of the device library to the project was completed. You can see that the AAR file name has been added to the Android Studio Project tree.




3.5.3 Dependency check of DeviceLibrary (AAR)


The registration of the device library was completed with "3.5.2 Registering DeviceLibrary (p.17)". However, somehow the dependency relationship of the DeviceLibrary to the project is not set correctly in some cases.

If the dependency is not set correctly, "3.5.4 Registering Help files (Javadoc) (p.23)" can not be done correctly, in that case follow the explanation in this section.


First, select "Project Structure ..." from File menu.




Open the "Dependencie" tab and check if "DeviceLibrary" (red frame in the figure below) exists. If it exists, subsequent operations are unnecessary.




If it does not exist, tap "+ button" at right end and select "Module dependency".



Confirm that "DeviceLibrary" is displayed as shown below and tap "OK".



By the above, "DeviceLibrary" has been added to the tab of "Dependencies".



3.5.4 Registering Help files (Javadoc)


This section explains how to enable pop-up help (pops up help message when you move the cursor to the function name) of Device Library.

First, associate Javadoc which is the help file of Device Libraries to Device Library registered to Android Studio.

The Javadoc file can be placed anywhere as long as it can be referenced on the PC. It assumes that it is placed in the "docs/DeviceLibrary" folder here.

When registration of the device library is completed, a xml file whose name is same as the library is automatically created under the "". Idea" folder. At moment, the item "<JAVADOC>" in this xml file has not been set. Specify the location of the javadoc file (folder path with index.html) in this item "<JAVADOC>".


```
<JAVADOC>
<root url="file://$PROJECT_DIR$/app/docs/DeviceLibrary" />
</JAVADOC>
```




By the above, the registration of the help file was completed.

Next, enable "Quick documentation on mouse move" which is the function of Android Studio.

Select "Settings ..." from File menu of Android Studio.



Next, check a box of "Show quick documentation on mouse move".



Now, if you hover the mouse cursor over the function name, help of the function will be poped up.




3.5.5 Updating of DeviceLibrary (AAR)

In order to update the device control library registered in the project of Android Studio (exchange to the new version), once you need to unregister (unassociate) them and register new one.

This section explains how to unregister (unassociate) them from the project.


(1) Unassociate Library (AAR)

Open your project in Android Studio and select [File] -> [Project Structure ...]. Select "app" from "Modules" in the left frame and open the "Dependencies" tab. Select DeviceLibrary and press the right "-" button to cancel the association.




(2) Unregister Library (AAR)

Next, select "DeviceLibrary" from "Modules" in the left frame and tap "- button" in the upper left.




A dialog to confirm deletion of DeviceLibrary appears, so tap [Yes].



By the above, Device Library was unregistered. Follow "3.5Installing and Updating Device Library(p.17)" to register the new Device Library.

3.6 How to use the DeviceLibrary (AAR)

To use an AAR file, just like jar, it is needed to inport it in order to create class object.



If a class that has not been imported is used, popup message as shown below is comes.

```
Button button_clearLaunchApplication;

ipp.casio.ht.devicelibrary.KeyLibrary? Alt+Enter

public KeyLibrary keyLib;

private final View.OnClickListener mButtonClickListener = (v) → {
    int returnCode = 0;
    String strToast = "";

4_0.xml

KeyLibrary.ApplicationInfo applicationInfo = new KeyLibrary.ApplicationInfo();
    applicationInfo.packageName = "";
    applicationInfo.activityName = "";
```

4. Application development and debug

In order to develop / debug applications using IT-G400, the following preparation is necessary.


- (1) Enable USB debugging (ADB connection) of IT-G400.
- (2) Install IT-G400 USB driver to your PC.
- (3) Set PATH to the debug tools on your PC.

These steps are described below.


4.1 Enabling USB debugging

Since USB debugging is a function for developers, you first need to activate the Developer options by the following procedure.

Open [Settings] \rightarrow [About phone] and tap "Build number" on the bottom line seven times, [Developer options] is added above [About phone].



Tap [Developer options] and enable "USB debugging" on the opened screen.




4.2 Installing USB driver


Install the USB driver for connecting the IT-G400 and PC with the ADB (Android Debug Bridge) protocol.

Files necessary for installation are downloaded as described in "3.4 Downloading Android SDK and USB driver (p.15)".


Connect the IT-G400 to a PC using a USB cable or a USB cradle. Then, open the Device Manager by [Control Panel] \rightarrow [Hardware and Sound] \rightarrow [Device Manager].




In the Device Manager, "Android" is displayed as an unknown device as shown below.




By right-click the red frame ("Android") in the above figure, displays its properties, and press [Update Driver].




When the dialog below is displayed, press "Let me pick from a list of drivers on my computer" at the bottom. In the driver list, with "Show all devices" is highlighted and press [Next].



When you click [Hard Disk...] in the displayed dialog, a dialog box for specifying the location of the driver opens, so click [Browse...] to open the file dialog box. In the file dialog box, search for "extras¥google¥usb_driver¥android_winusb.inf" under the "Android SDK Installation Location" that you took note in "3.4 Downloading Android SDK and USB driver (p.15)" and specify it.



The following driver selection screen will appear. Select "Android Composite ADB Interface" and press [Next]. Answer "Yes" to "Driver Update Warning" and press "Install" of "Windows Security" dialog.




By the above, the installation of the USB driver for ADB protocol was completed.

4.3 Settings for ADB (Android Debug Bridge)

In order to use Android SDK tools such as adb from the command prompt, it is needed to add the path to Android SDK to the system environment variable. Add the following two paths.

The "tools" folder under "Android SDK Installation Location" that you took note. The "platform-tools" folder under "Android SDK Installation Location".



In the above example, the path to add is as follows.

C:\Users\u20a4casio\u22a4AppData\u22a4local\u22a4Android\u22ask\u22astools

C:\Users\u00e4casio\u00e4AppData\u00e4local\u00e4Android\u00e4sdk\u00e4platform-tools